

**Known issues:**

1. Entering BIOS setup <F2> or selecting a boot device <F10> is difficult
2. The Intel® Graphics Media Accelerator driver is displayed as Failed in the Intel Express Installer for Intel® Mobile Board MGM45RM
3. System will not resume from Standby (S3) when using Intel® Core™ 2 Duo T5670 and T5870 processors

**Solutions:**

**1. Issue:** Entering BIOS setup <F2> or selecting a boot device <F10> is difficult

**Solution:**

The issue has been resolved in BIOS revision RMM4510H.86A.0033 or later. The latest BIOS version for Mobile Board MGM45RM is available for download from the <http://downloadcenter.intel.com> website.

**2. Issue:** The Intel® Graphics Media Accelerator driver is displayed as Failed in the Intel Express Installer for Intel® Mobile Board MGM45RM

**Solution:**

1. Even though the installation for Intel® Graphic Media Accelerator displays as a Failure, the driver is actually installed successfully. Allow the Express Installer to finish all driver and software installations. The next revision of the Express Installer DVD for Mobile Board MGM45RM will have this problem resolved.
2. During the Express Installer installation for the Realtek\* Audio Driver, two "New Devices Detected" windows will appear. Selecting the "cancel" button on both windows will result in the Graphics Media Accelerator driver status displayed as "successful."

**3. Issue:** System does not resume from Standby (S3) when using Intel® Core™ 2 Duo T5670 and T5870 processors

**Solution:**

The issue has been resolved in BIOS revision RMM4510H.86A.0033 or later. The latest BIOS version for Mobile Board MGM45RM is available for download from the <http://downloadcenter.intel.com> website.